

YOU WILL BE CHARGED FOR COLOR COPIES UNLESS YOU MAKE ARRANGEMENTS FOR B/W WITH A HIATT PRINTING REPRESENTATIVE PRIOR TO SENDING YOUR JOB TO BE PRINTED.

- 1. Connect your computer to the hiatt Wi-Fi Network.
- 2. Go to www.hiattprinting.com
 - On the left hand side of the page click **Printing Tools**
 - Select the bizhub C654 Driver for your version of windows to download the installation files. Click [Save] and choose a location to save the installer and



click [Save] again.

- Double click win_x86.exe (win_x64.exe) to extract the driver set-up files. In the "Extract to:" window, click [Browse...] to choose a location to save the Install Printer folder. Then click [Extract].
- 3. In the Install Printer folder, double click on Setup.exe.
- 4. Read the license agreement, then click [AGREE].





Wi-Fi Printing Instructions

Windows

5. Select [Install printers/MFPs], then click [Next].

Connected printers are detected.

/C654

- For Windows Vista/7/8/Server 2008/ Server 2008 R2/Server 2012, you can select [Preference for IPv4] or [Preference for IPv6]. The address has the preference when detected in both IPv4 and IPv6.
- 6. Select the KONICA MINOLTA bizhub C654, then click [Next].
 - If the connection to the machine cannot be recognized, it is not displayed in the list. In such a case, select [Specify the Printer/ MFP Except for the above. (IP Address, Host Name...)], and manually specify the IP address 192.168.1.100

Se	elect menu to setup	~ ~
lect menu to setup.		
Install printers/MFPs		
Install printers on this com detected automatically.	puter. Network printers and USB	-connected printers are
	Network printer	
	Preference for IPv4	Preference for IPv6
Update Printer Driver		
Update the printer driver in Notice: After updating,	nstalled on this computer to the you will need to restart the o	latest version. computer.
🔿 Uninstall Printer Driver		
Uninstall a printer driver fro Notice: After uninstalling	m this computer. g, you will need to restart th	e computer.

192.168.1.20	Not installed
Search Setting	Update List
(IP Address, Host Name	e)
	Search Setting

7. Select the check box of the printer driver(s) you want to install, then click [Next].

KONICA MINOLTA Printer Installer	- Selecting the installation setting the installation	setting	X	
Select the installation setting.				
Driver Language Components to Be Installed		English	•	Fax not available.
KONICA MINOLTA C3649	SeriesPCL SeriesPS			
Help	Previous	Next	Cancel	



Wi-Fi Printing Instructions Windows

8. Check the items to be installed, and click [Install].



- 9. If necessary, change the printer name.
- 10. Select the printer you want to print to and click [Print Setting].
 - In the "Document Properties" window, select the Basic tab and click [Authentication/Account Track...]. Enter the Department Name: *hiatt* and Password: *hiatt* and click [OK]. Click [OK] in the "Document Properties" window, then click [Finish].

fault Printer		
	~	
KONICA MINOLTA C364SeriesPCL		
ded Printers		
KONICA MINOLTA C364SeriesPCL (192.168.1.20) KONICA MINOLTA C364SeriesPS (192.168.1.20)	Rename Printer	
KONICA MINOLTA C364SeriesFAX (192.168.1.20)	Property	
	Print Setting	



This completes the installation process of the printer driver.

YOU WILL BE CHARGED FOR COLOR COPIES UNLESS YOU MAKE ARRANGEMENTS FOR B/W WITH A HIATT PRINTING REPRESENTATIVE PRIOR TO SENDING YOUR JOB TO BE PRINTED.